

Sentinel Protection Installer Version 7.6.9 – Release Notes

This document contains information on new features, supported/unsupported platforms, and known issues in SentinelTM Protection Installer version 7.6.9 release.

Product Overview

Sentinel Protection Installer is an integrated installer of the Sentinel System Driver, Sentinel Security Runtime, Sentinel Protection Server, and Sentinel Keys Server.

Component	Version Supported
Sentinel System Driver	7.6.0
Sentinel Security Runtime	1.0.1
Sentinel Protection Server	7.6.5.0
Sentinel Keys Server	1.3.6.0

Sentinel Protection Installer 7.6.9 supports following versions of its components:

Platforms Supported

This installer can be run on Microsoft Windows XP(32-bit and 64-bit), Server 2008 R2 (64-bit), Windows 7 (32-bit and 64-bit), Windows 8 (32-bit and 64-bit), Windows Server 2012 (64-bit), Windows 8.1 (32-bit and 64-bit), Windows 10 (32-bit and 64-bit) and Windows Server 2016 (64-bit).

Note: For information on the platforms supported by Sentinel Protection Installer components, refer to the *Sentinel Protection Installer ReadMe*.

Enhancements and Problems Corrected in This Release

The following are the enhancements and fixes in this release:

- For Sentinel System Driver, the support for Windows 10 Credential Guard and Device Guard has been added.
- Parallel Drivers installation has been removed from the default installation path. If required, a customer can install it from the custom installation path.
- The support for Applets has been removed. Now Sentinel License Monitor requires Javascript to be enabled to run.
- The dependency on OpenSSL has been removed.

Known Issues

- Standard users cannot uninstall Sentinel Protection Installer from the Control Panel using the Uninstall option on Windows Server 2008, Windows Server 2008 R2, Windows Vista, Windows 7, Windows 8, Windows Server 2012, and Windows 8.1 systems. It is recommended that the standard users should select Change and subsequently select Remove from Program Maintenance dialog of Sentinel Protection Installer to perform uninstallation on Windows Server 2008, Windows Server 2008 R2, Windows Vista, and Windows 7, Windows 8, Windows Server 2008, Windows Server 2008 R2, Server 2008, Windows 8.1 systems.
- On Windows Server 2008 R2 and Windows 7, the Program Compatibility Assistant dialog box may appear when you exit the driver configuration program (*SetupSysDriver.exe*). Click This program installed correctly to prevent the dialog box from appearing in the future.

If you are linking the driver configuration program to your own installer, we recommend renaming the application and the manifest file to prevent the **Program Compatibility Assistant** dialog box from appearing. For example, you can rename the application and the manifest file to *CfgSysDriver.exe* and *CfgSysDriver.exe.manifest*.

Removed Platform Support

The Sentinel Protection Installer no longer supports Sentinel Protection Server on the following platforms:

- Windows 98
- Windows ME
- *Note:* Sentinel Protection Installer 7.5.0 is the last release that supports Sentinel Protection Server on Windows 98 and Windows ME.

Contacting Technical Support

If you have questions, need additonal assistance, or encounter a problem, please contact Technical Support using the options provided below:

Contact Method	Contact Information
Address	SafeNet, Inc. 4690 Millennium Drive Belcamp, Maryland 21017 USA
Phone	United States: 1-800-545-6608
	International- 1-410-931-7520
Email	support@safenet-inc.com
Support and Downloads	www.safenet-inc.com/Support Provides access to the SafeNet Knowledge Base and quick downloads for various products.
Technical Support Customer Portal	https://serviceportal.safenet-inc.com Existing customers with a Technical Support Customer Portal account can log in to manage incidents, get the latest software upgrades, and access the SafeNet Knowledge Base.

© Copyright 2017, SafeNet, Inc. All rights reserved. *http://www.safenet-inc.com* SafeNet and Sentinel, are either registered trademarks or trademarks of SafeNet, Inc. All other product names referenced herein are trademarks or registered trademarks of their respective manufacturers.

> Part Number 007152-001, Revision P September 2017